

Chapter Six

Internet Protocol (IP) and IP Addressing

IP

- The **Internet Protocol (IP)** is a protocol used for **communicating data** across a **packet-switched** internetwork using the Internet Protocol Suite, also referred to as TCP/IP.
- IP is the **primary protocol in the Internet Layer** of the Internet Protocol Suite and has the task of **delivering** distinguished protocol datagrams (packets) from the **source host** to the **destination host** solely **based on their addresses**. For this purpose the Internet Protocol defines addressing methods and structures for datagram encapsulation.
- The first major version of addressing structure, now referred to as Internet Protocol Version 4 (**IPv4**) is still the dominant protocol of the Internet, although the successor, Internet Protocol Version 6 (**IPv6**), is being deployed actively worldwide (128 bits).

IP Addressing

- Communication at the network layer is **host-to-host** (**computer-to-computer**); a computer somewhere in the world needs to communicate with another computer somewhere else in the world.
- Usually, computers communicate through the Internet.
- The packet transmitted by the sending computer may pass through several **LANs** or **WANs** before reaching the destination computer.
- For this level of communication, we need a **global addressing scheme**; we use the term **IP address** to mean a **logical address** in the network layer of the TCP/IP protocol suite.

IPv4 Addresses

- An **IPv4** address is a **32-bit** address that uniquely and universally defines the connection of a device (for example, a computer or a router) to the Internet.
- IPv4 addresses are **unique and universal**.
- They are unique in the sense that each address defines **one, and only one**, connection to the Internet.
- Two devices on the Internet **can never have the same address at the same time**.

Address Space

- A protocol such as IPv4 that defines addresses has an **address space**. An address space is the **total number of addresses** used by the protocol.
- If a protocol uses **N bits** to define an address, the address space is **2^N** because each bit can have two different values (**0 or 1**) and N bits can have 2^N values.
- IPv4 uses **32-bit addresses**, which means that the address space is **2^{32}** or **4,294,967,296** (more than 4 billion). This means that, **theoretically**, if there were **no restrictions**, more **than 4 billion devices** could be connected to the Internet.
- We will see shortly that the actual number is much less because of the **restrictions imposed on the addresses**.


- There are two prevalent notations to show an IPv4 address: **binary notation** and **dotted-decimal notation**.
- **Binary Notation**
 - In binary notation, the IPv4 address is displayed as 32 bits. Each octet is often referred to as a byte. So it is common to hear an IPv4 address referred to as a 32-bit address or a 4-byte address. The following is an example of an IPv4 address in binary notation:


01110101 10010101 00011101 00000010

- **Dotted-Decimal Notation**
 - To make the IPv4 address more compact and easier to read, Internet addresses are usually written in decimal form with a decimal point (dot) separating the bytes. The following is the dotted-decimal notation of the above address:

117.149.29.2

Example: *Dotted-decimal notation and binary notation for an IPv4 address*





Example 1

Change the following IPv4 addresses from binary notation to dotted-decimal notation.

a. 10000001 00001011 00001011 11101111


b. 11000001 10000011 00011011 11111111

Solution

We replace each group of 8 bits with its equivalent decimal number and add dots for separation.

a. 129.11.11.239

b. 193.131.27.255



Example 2

Change the following IPv4 addresses from dotted-decimal notation to binary notation.

a. 111.56.45.78


b. 221.34.7.82

Solution

We replace each decimal number with its binary equivalent.

a. 01101111 00111000 00101101 01001110

b. 11011101 00100010 00000111 01010010



Example 3

Find the error, if any, in the following IPv4 addresses.

- a. 111.56.045.78*
- b. 221.34.7.8.20*
- c. 75.45.301.14*
- d. 11100010.23.14.67*

Solution

- a. There must be no leading zero (045).*
- b. There can be no more than four numbers.*
- c. Each number needs to be less than or equal to 255.*
- d. A mixture of binary notation and dotted-decimal notation is not allowed.*

Classful Addressing

- IPv4 addressing, at its inception, used the concept of **classes**. This architecture is called **classful addressing**.
- In classful addressing, the address space is divided into five classes: **A, B, C, D, and E**. Each class occupies some part of the address space.


Finding the classes in binary and dotted-decimal notation

	First byte	Second byte	Third byte	Fourth byte
Class A	0			
Class B	10			
Class C	110			
Class D	1110			
Class E	1111			

a. Binary notation

	First byte	Second byte	Third byte	Fourth byte
Class A	0–127			
Class B	128–191			
Class C	192–223			
Class D	224–239			
Class E	240–255			

b. Dotted-decimal notation



Example 4

Find the class of each address.

- a.* 00000001 00001011 00001011 11101111
- b.* 11000001 10000011 00011011 11111111
- c.* 14.23.120.8
- d.* 252.5.15.111

Solution

- a.* The first bit is 0. This is a class A address.
- b.* The first 2 bits are 1; the third bit is 0. This is a class C address.
- c.* The first byte is 14; the class is A.
- d.* The first byte is 252; the class is E.

Classes and Blocks

- One problem with classful addressing is that each class is divided into a fixed number of blocks with each block having a fixed size

<i>Class</i>	<i>Number of Blocks</i>	<i>Block Size</i>	<i>Application</i>
A	128	16,777,216	Unicast
B	16,384	65,536	Unicast
C	2,097,152	256	Unicast
D	1	268,435,456	Multicast
E	1	268,435,456	Reserved

Number of Blocks for class A = 2^7

Number of Blocks for class B = 2^{14}

Number of Blocks for class C = 2^{21}

Block size for class A = 2^{24}

Block size for class B = 2^{16}

Block size for class C = 2^8

...

- Previously, when an organization requested a block of addresses, it was granted **one in class A, B, or C**.
- **Class A** addresses were **designed for large organizations** with a large number of attached hosts or routers.
- **Class B** addresses were designed for **midsize organizations** with tens of thousands of attached hosts or routers.
- **Class C** addresses were designed for **small organizations** with a small number of attached hosts or routers.
- A block in **class A address is too large** for almost any organization. This means most of the addresses in class A were wasted and were not used.
- A block in **class B is also very large**, probably too large for many of the organizations that received a class B block.
- A block in **class C is probably too small** for many organizations.

Network ID and Host ID

- In classful addressing, an IP address in class A, B, or C is divided into **network ID and host ID**.
- These parts are of varying lengths, depending on the class of the address.
- In **class A**, **one byte** defines the **network ID** and **three bytes** define the **host ID**.
- In **class B**, **two bytes** define the **network ID** and **two bytes** define the **host ID**.
- In **class C**, **three bytes** define the **network ID** and **one byte** defines the **host ID**.

Mask

- Although the length of the network ID and host ID (in bits) is predetermined in classful addressing, we can also use a mask (also called the **default mask**), a 32-bit number made of **contiguous 1s** followed by **contiguous 0s**. The masks for classes A, B, and C are shown below
- The mask can help us **to find the network ID** and the **host ID**. For example, the mask for a class A address has eight 1 s, which means the first 8 bits of any address in class A define the **network ID**; the next **24 bits** define the host ID.

<i>Class</i>	<i>Binary</i>	<i>Dotted-Decimal</i>	<i>CIDR</i>
A	11111111 00000000 00000000 00000000	255.0.0.0	/8
B	11111111 11111111 00000000 00000000	255.255.0.0	/16
C	11111111 11111111 11111111 00000000	255.255.255.0	/24

Subnetting

- During the era of **classful addressing**, subnetting was introduced.
- If an organization was granted a **large block in class A or B**, it could divide the addresses into several contiguous groups and assign each group to smaller networks (called **subnets**) or, in rare cases, share part of the addresses with neighbors.
- **Subnetting increases the number of 1s in the mask.**

Address Depletion



- The **flaws in classful** addressing scheme combined with the **fast growth of the Internet** led to the **near depletion** of the available addresses.
- Yet the number of devices on the Internet is much **less than the 2^{32}** address space.
- We have **run out of class A and B addresses**, and a **class C block is too small** for most midsize organizations.
- One solution that has **alleviated** the problem is the idea of **classless addressing**.

Classless Addressing

- To overcome address depletion and give more organizations access to the Internet, classless addressing was designed and implemented.
- In this scheme, there are **no classes**, but the addresses are **still granted in blocks**.
- Address Blocks
 - In classless addressing, when an entity, small or large, needs to be connected to the Internet, it is granted a **block (range) of addresses**.
 - The size of the block (**the number of addresses**) varies based on the **nature and size** of the entity.
 - For example, a **household** may be given only **two** addresses; a **large organization** may be given **thousands** of addresses.
 - An **ISP**, as the Internet service provider, may be given **thousands or hundreds of thousands** based on the number of customers it may serve.

Restriction

- To simplify the handling of addresses, the Internet authorities impose three restrictions on classless address blocks:
 1. The addresses in a block must be contiguous, one after another.
 2. The number of addresses in a block must be a power of 2 (1, 2, 4, 8).
 3. The first address must be evenly divisible by the number of addresses.



- The above figure shows a block of addresses, in both *binary* and *dotted-decimal* notation, granted to a small business that needs **16 addresses**.
- We can see that the restrictions are applied to this block. The addresses are **contiguous**. The number of addresses is a power of 2 (**$16 = 2^4$**), and the first address is divisible by 16. The first address, when converted to a decimal number, is **3,440,387,360**, which when divided by **16** results in **215,024,210**.

Classless addressing Mask

- A better way to define a block of addresses is to select any address in the block and the mask.
- As we discussed before, a mask is a 32-bit number in which the n leftmost bits are 1s and the $32 - n$ rightmost bits are 0s.
- However, in classless addressing the mask for a block can take any value from 0 to 32. It is very convenient to give just the value of n preceded by a slash (CIDR – Classless Inter Domain Routing notation).
- The address and the $/n$ notation completely define the whole block (the first address, the last address, and the number of addresses).

-

First Address

- The first address in the block can be found by setting the **32 - n rightmost** bits in the binary notation of the address to **0s**.
- Example 5
- *A block of addresses is granted to a small organization. We know that one of the addresses is **205.16.37.39/28**. What is the first address in the block?*
- *Solution*
- *The binary representation of the given address is*
 - *11001101 00010000 00100101 00100111*
- *If we set 32–28 rightmost bits to 0, we get*
 - *11001101 00010000 00100101 00100000*
 - *or*
205.16.37.32.

Last Address

- The last address in the block can be found by setting the 32 - n rightmost bits in the binary notation of the address to 1s.
- Example 6
- *Find the last address for the block in Example 5.*
- *Solution*
- *The binary representation of the given address is*
 - 11001101 00010000 00100101 00100111
- *If we set 32 – 28 rightmost bits to 1, we get*
 - 11001101 00010000 00100101 00101111
 - or
 - 205.16.37.47

Number of Addresses

- The number of addresses in the block is the difference between the last and first address. It can easily be found using the formula 2^{32-n} .
- Example 7
- *Find the number of addresses in Example 5.*
- *Solution*
- *The value of n is 28, which means that number of addresses is 2^{32-28} or 16.*


- Another way to find the first address, the last address, and the number of addresses is *to represent the mask as a 32-bit binary* (or 8-digit hexadecimal) number. This is particularly useful when we are writing a program to find these pieces of information. In the above example the /28 can be represented as

- **11111111 11111111 11111111 11110000**

(twenty-eight 1s and four 0s).

Find


- *a. The first address*
- *b. The last address*
- *c. The number of addresses.*



Solution


- a. The first address can be found by **ANDing** the given addresses with the mask. ANDing here is done bit by bit. The result of ANDing 2 bits is 1 if both bits are 1s; the result is 0 otherwise.

Address:	11001101	00010000	00100101	00100111
Mask:	11111111	11111111	11111111	11110000
First address:	11001101	00010000	00100101	00100000



*b. The last address can be found by **ORing** the given addresses with the complement of the mask. ORing here is done bit by bit. The result of ORing 2 bits is 0 if both bits are 0s; the result is 1 otherwise. The complement of a number is found by changing each 1 to 0 and each 0 to 1.*

Address:	11001101	00010000	00100101	00100111
Mask complement:	00000000	00000000	00000000	00001111
Last address:	11001101	00010000	00100101	00101111

- 
- c. *The number of addresses can be found by complementing the mask, interpreting it as a decimal number, and adding 1 to it.*

Mask complement: 00000000 00000000 00000000 00001111

Number of addresses: $15 + 1 = 16$

Network Addresses

- A very important concept in IP addressing is the network address.
- When an organization is given a block of addresses, the organization is **free to allocate the addresses** to the devices that need to be connected to the Internet.
- The **first address in the class**, however, is normally (not always) **treated as a special address**.
- The first address is called the **network address** and defines the **organization network**.
- It defines the organization itself to the **rest of the world**.
- The first address is the one that is used by **routers** to direct the message sent to the organization from the outside.

Hierarchy

- IP addresses, like other addresses or identifiers we encounter these days, have levels of hierarchy.
- For example, a telephone network in Ethiopia has three levels of hierarchy.
- The leftmost three digits (251) define the country code, the next three digits (011, for example) define the area, the last seven digits (1112343, for example) define the subscriber number.

Two-Level Hierarchy: No Subnetting


- An IP address can define only two levels of hierarchy when **not subnetted**.
- The **n leftmost bits of the address x.y.z.t/n** define the **network** (organization network); the **32 - n** rightmost bits define the particular host (computer or router) to the network.
- The two common terms are **prefix** and **suffix**.
- The part of the address that defines the network is called the **prefix**; the part that defines the host is called the **suffix**.
- The prefix is **common to all addresses** in the network; the suffix changes from one device to another.

Three-Levels of Hierarchy: Subnetting

- An organization that is granted a large block of addresses may want to create clusters of networks (called **subnets**) and divide the addresses between the different subnets.
- The rest of the world still sees the organization as **one entity**; however, internally there are **several subnets**.
- All messages are sent to the router address that connects the organization to the rest of the Internet; the router routes the message to the **appropriate subnets**.
- The organization, however, needs to create **small sub blocks** of addresses, each assigned to specific **subnets**. The organization has its own mask; each subnet must also have its own.

Example 7

- Suppose an organization is given the block **17.12.14.0/26**, which contains 64 addresses. The organization has three offices and needs to divide the addresses into **three sub blocks** of **32**, **16**, and **16** addresses.
- We can find the new masks by using the following arguments:
 1. Suppose the mask for the first subnet is n_1 , then 2^{32-n_1} must be 32, which means that **$n_1 = 27$** .
 2. Suppose the mask for the second subnet is n_2 , then 2^{32-n_2} must be 16, which means that **$n_2 = 28$** .
 3. Suppose the mask for the third subnet is n_3 , then 2^{32-n_3} must be 16, which means that **$n_3 = 28$** .
- This means that we have the masks **27, 28, 28** with the organization mask being **26**.



More Levels of Hierarchy

- The structure of classless addressing does not restrict the number of hierarchical levels.
- An organization can divide the granted block of addresses into sub blocks.
- Each sub block can in turn be divided into **smaller sub blocks**. And so on.
- One example of this is seen in the **ISPs**. A **national ISP** can divide a granted large block into smaller blocks and assign each of them to a **regional ISP**. A **regional ISP** can divide the block received from the national ISP into smaller blocks and assign each one to a **local ISP**.
- A **local ISP** can divide the block received from the regional ISP into smaller blocks and assign each one to a **different organization**.
- Finally, an organization can divide the received block and make **several subnets out of it**.

Address Allocation

- The next issue in classless addressing is address allocation. How are the blocks allocated?
- The ultimate responsibility of address allocation is given to a **global authority** called the Internet Corporation for Assigned Names and Addresses (**ICANN**).
- However, ICANN does not normally allocate addresses to **individual organizations**. It assigns a large block of addresses to an ISP.
- Each ISP, in turn, divides its assigned block into smaller sub blocks and grants the sub blocks to its customers.
- In other words, an ISP receives one large block to be distributed to its **Internet users**. This is called **address aggregation**: many blocks of addresses are aggregated in one block and granted to one ISP.

Example 8

An ISP is granted a block of addresses starting with 190.100.0.0/16 (65,536 addresses). The ISP needs to distribute these addresses to three groups of customers as follows:

- a. The first group has 64 customers; each needs 256 addresses.*
- b. The second group has 128 customers; each needs 128 addresses.*
- c. The third group has 128 customers; each needs 64 addresses.*

Design the sub blocks and find out how many addresses are still available after these allocations.

Group 1

For this group, each customer needs 256 addresses. This means that 8 bits are needed to define each host. The prefix length is then $32 - 8 = 24$. The addresses are

<i>1st Customer:</i>	<i>190.100.0.0/24</i>	<i>190.100.0.255/24</i>
<i>2nd Customer:</i>	<i>190.100.1.0/24</i>	<i>190.100.1.255/24</i>
<i>...</i>		
<i>64th Customer:</i>	<i>190.100.63.0/24</i>	<i>190.100.63.255/24</i>
<i>Total = $64 \times 256 = 16,384$</i>		

Group 2

For this group, each customer needs 128 addresses. This means that 7 bits are needed to define each host. The prefix length is then $32 - 7 = 25$. The addresses are

<i>1st Customer:</i>	<i>190.100.64.0/25</i>	<i>190.100.64.127/25</i>
<i>2nd Customer:</i>	<i>190.100.64.128/25</i>	<i>190.100.64.255/25</i>
<i>...</i>		
<i>128th Customer:</i>	<i>190.100.127.128/25</i>	<i>190.100.127.255/25</i>
<i>Total = $128 \times 128 = 16,384$</i>		

Group 3

For this group, each customer needs 64 addresses. This means that 6 bits are needed to each host. The prefix length is then $32 - 6 = 26$. The addresses are

<i>1st Customer:</i>	<i>190.100.128.0/26</i>	<i>190.100.128.63/26</i>
<i>2nd Customer:</i>	<i>190.100.128.64/26</i>	<i>190.100.128.127/26</i>
<i>...</i>		
<i>128th Customer:</i>	<i>190.100.159.192/26</i>	<i>190.100.159.255/26</i>
<i>Total = $128 \times 64 = 8192$</i>		

Number of granted addresses to the ISP: 65,536

Number of allocated addresses by the ISP: 40,960



Number of available addresses: 24,576

Network Address Translation (NAT)

- Many users start to have more hosts to be connected to the internet
- IP addresses are in depletion
- Solution: NAT
- NAT enables a user to have a large set of addresses internally and one address, or a small set of addresses, externally. The traffic inside can use the large set; the traffic outside, the small set.

<i>Range</i>			<i>Total</i>
10.0.0.0	to	10.255.255.255	2^{24}
172.16.0.0	to	172.31.255.255	2^{20}
192.168.0.0	to	192.168.255.255	2^{16}

Site using private addresses




Reading Assignment:

1. Read how NAT works
2. Investigate the global IP address scheme of Adama University and how they used it in NAT

IPv6 ADDRESSES

- Despite all short-term solutions, address depletion is still a long-term problem for the Internet. This and other problems in the IP protocol itself have been the motivation for IPv6.
- An IPv6 address is 128 bits or 32 hexadecimal digits long.



Abbreviated IPv6 addresses

Original

FDEC ■ 0074 ■ 0000 ■ 0000 ■ 0000 ■ B0FF ■ 0000 ■ FFF0



Abbreviated

FDEC ■ 74 ■ 0 ■ 0 ■ 0 ■ B0FF ■ 0 ■ FFF0



More abbreviated

FDEC ■ 74 ■ ■ B0FF ■ 0 ■ FFF0

Gap

Example 9

Expand the address 0:15::1:12:1213 to its original.

Solution

We first need to align the left side of the double colon to the left of the original pattern and the right side of the double colon to the right of the original pattern to find how many 0s we need to replace the double colon.

XXXX:XXXX:XXXX:XXXX:XXXX:XXXX:XXXX:XXXX
0: 15: : 1: 12:1213

This means that the original address is.


0000:0015:0000:0000:0000:0001:0012:1213

ADDRESS MAPPING


- The delivery of a packet to a host or a router requires two levels of addressing: **logical** and **physical**. We need to be able to map a logical address to its corresponding physical address and vice versa. This can be done by using either static or dynamic mapping.
- IP is used for logical addressing
- MAC is used for physical addressing in a local network such as Ethernet

Mapping Logical to Physical Address: ARP

- Anytime a host or a router has an IP datagram to send to another host or router, it has the logical (IP) address of the receiver.
- The logical (IP) address is obtained from the DNS if the sender is the host or it is found in a routing table if the sender is a router.
- But the IP datagram must be encapsulated in a frame to be able to pass through the physical network. This means that the sender needs the physical address of the receiver. The host or the router sends an ARP query packet.
- The packet includes the physical and IP addresses of the sender and the IP address of the receiver. Because the sender does not know the physical address of the receiver, the query is broadcast over the network



a. ARP request is broadcast



b. ARP reply is unicast

Mapping Physical to Logical Address: RARP

- There are occasions in which a host knows its physical address, but needs to know its logical address. This may happen in two cases:
 1. A diskless station is just booted. The station can find its physical address by checking its interface, but it does not know its IP address.
 2. An organization does not have enough IP addresses to assign to each station; it needs to assign IP addresses on demand. The station can send its physical address and ask for a short time lease.

- Reverse Address Resolution Protocol (RARP) finds the logical address for a machine that knows only its physical address. Each host or router is assigned one or more logical (IP) addresses, which are unique and independent of the physical (hardware) address of the machine. To create an IP datagram, a host or a router needs to know its own IP address or addresses. The IP address of a machine is usually read from its configuration file stored on a disk file.
- The machine can get its physical address (by reading its NIC, for example), which is unique locally. It can then use the physical address to get the logical address by using the RARP protocol. A RARP request is created and broadcast on the local network. Another machine on the local network that knows all the IP addresses will respond with a RARP reply.

ICMP

- The IP protocol has no error-reporting or error-correcting mechanism. The IP protocol also lacks a mechanism for host and management queries. The **Internet Control Message Protocol (ICMP)** has been designed to compensate for the above two deficiencies. It is a companion to the IP protocol.
- PING and TRACEROUTE are two tools for ICMP